

# Release Notes

**Product name: XX Configuration Software**

**Version: 2.6.1.0 (EN)**

**Date: 03/18/2024**

## 1. Introduction

### *Purpose*

The purpose of this document is to communicate the new features and changes in this release of "XX Configuration Software".

XX Configuration Software is a Windows application dedicated to the configuration of ultrasonic sensors (XX) from the manufacturer Télémécanique Sensors.

This release notes document describes the evolutions for "XX Configuration Software" compared to the previous version.

### *Definitions, acronyms and abbreviations*

XX: Ultrasonic sensor.

XXBox (XXZBOX01): Accessory allowing communication between the PC and the sensor.

### *Compatibility*

This version is compatible with any previous software version of "XX Configuration Software". Any firmware version of the XXBox is also compatible.

## 2. About

- Remove SESU / SUT software,
- Changed the software update process,
- Removed admin rights for shortcuts,
- Add customer profile (panel settings) feature.

## 3. Known defects and troubleshooting

### Data recording (echo display)

If some recording data (XML or XLSX) in "Echo display" mode are found to be lost, you must restart the "XX Configuration Software" application. Unplug and then reconnect the XXBox power supply cable. Restart the application.

### Communication error (disconnection of XXBox USB cable)

A frequent repeated action of disconnection and then reconnection of the XXBox USB cable to the PC can severely damage the XXBox, which may lead to a loss of configuration of the XXBox.

Some disconnections of the USB cable, during transfer of data between the PC and the sensor, can cause stops of the application "XX Configuration Software". In this case, you must restart the application.